

### 4.4.

#### bash

.bash\_profile

lfs

```
cat > ~/.bash_profile << "EOF"
exec evn -i HOME=$HOME      =$TERM PS1='\u:\w\$ ' /bin/bash
EOF
```

```
lfs      " - "      su      lfs
      /etc/profile(      가      )
.bash_profile      .bash_profile      exec env -i.../bin/bash
HOME,TERM  PS1      가
      가
      non-login      , /etc/profile      .bash_profile
      .bashrc      ..bashrc
```

```
cat > ~/.bashrc << "EOF"
set +h
umask 022
LFS=/mnt/lfs
LC_ALL=POSIX
LFS_TGT=$(uname -m)-lfs-linux-gnu
PATH=/usr/bin
if [ ! -L /bin ]; then PATH=/bin:$PATH; fi
PATH=$LFS/tools/bin:$PATH
CONFIG_SITE=$LFS/usr/share/config.site
export LFS LC_ALL LFS_TGT PATH CONFIG_SITE
EOF
```

#### .bashrc

- **set +h**  
 set +h      bash  
 PATH  
 /usr/bin    /bin  
 \$LFS/tools/bin
- **umask 022**  
 (umask) 022  
 (      가 open(2)      가  
 644 ,      755      ).
- **LFS=/mnt/lfs**  
 LFS
- **LC\_ALL=POSIX**  
 LC\_ALL      가      가  
 . LC\_ALL "POSIX" "C"(      )
- **LFS\_TGT=\$(uname -m)-lfs-linux-gnu**

LFS\_TGT

가

- **PATH=/usr/bin**

/bin /usr/bin

6

PATH /usr/bin/

/bin 가

- **if [ ! -L /bin ]; then PATH=/bin:\$PATH; fi**

/bin 가 PATH 가

- **PATH=\$LFS/tools/bin:\$PATH**

PATH \$LFS/tools/bin 5 가

가

- **CONFIG\_SITE=\$LFS/usr/share/config.site**

5 6 가 configure 가

/usr/share/config.site

- **export ...**

/etc/bash.bashrc

bash

가

LFS

lfs

. lfs



/etc/bash.bashrc가  
root

```
[ ! -e /etc/bash.bashrc ] || mv -v /etc/bash.bashrc  
/etc/bash.bashrc.NOUSE
```

lfs 가 ( 7 ) /etc/bash.bashrc

( )

8.35 "Bash-5.2.21"

LFS Bash  
LFS

/etc/bash.bashrc  
가

가 ( )  
make "parallel make"  
i9-13900K 8 P( ) 16 E( )  
가 , P 2 P 2  
32 가  
make가 32  
make -j32

```
make -j32
```

MAKEFLAGS

make

```
export MAKEFLAGS=-j32
```



`-j`     **make**     MAKEFLAGS

**make가**

5     6  
MAKEFLAGS

.bashrc

```
cat >> ~/.bashrc << "EOF"  
export MAKEFLAGS=-j$(nproc)  
EOF
```

`$(nproc)`

**bash**

```
source ~/.bash_profile
```

From:  
<https://www.gamu.kr/dokuwiki/> -

Permanent link:  
[https://www.gamu.kr/dokuwiki/linuxfromscratch/12.1/028-setting\\_up\\_the\\_environment?rev=1716812713](https://www.gamu.kr/dokuwiki/linuxfromscratch/12.1/028-setting_up_the_environment?rev=1716812713)

Last update: 2024/05/27 12:25

