

4.4.

bash

.bash_profile

lfs

```
cat > ~/.bash_profile << "EOF"
exec env -i HOME=$HOME TERM=$TERM PS1='\u:\w\$ ' /bin/bash
EOF
```

```
lfs      " - "      su      lfs
      /etc/profile(      가      )
.bash_profile      .bash_profile      exec env -i.../bin/bash
HOME,TERM  PS1      가
```

```
cat > ~/.bashrc << "EOF"
set +h
umask 022
LFS=/mnt/lfs
LC_ALL=POSIX
LFS_TGT=$(uname -m)-lfs-linux-gnu
PATH=/usr/bin
if [ ! -L /bin ]; then PATH=/bin:$PATH; fi
PATH=$LFS/tools/bin:$PATH
CONFIG_SITE=$LFS/usr/share/config.site
export LFS LC_ALL LFS_TGT PATH CONFIG_SITE
EOF
```

.bashrc

- **set +h**
 set +h bash
 PATH
 /usr/bin /bin
 \$LFS/tools/bin
- **umask 022**
 (umask) 022
 (가 open(2) 가
 644 , 755).
- **LFS=/mnt/lfs**
 LFS
- **LC_ALL=POSIX**
 LC_ALL 가 가
 . LC_ALL "POSIX" "C"()
- **LFS_TGT=\$(uname -m)-lfs-linux-gnu**

LFS_TGT

가

- **PATH=/usr/bin**

/bin /usr/bin

6

PATH /usr/bin/

/bin 가

- **if [! -L /bin]; then PATH=/bin:\$PATH; fi**

/bin 가 PATH 가

- **PATH=\$LFS/tools/bin:\$PATH**

PATH \$LFS/tools/bin 5 가

가

- **CONFIG_SITE=\$LFS/usr/share/config.site**

5 6 가 configure 가

/usr/share/config.site

- **export ...**

/etc/bash.bashrc

bash

가

LFS

lfs

. lfs



/etc/bash.bashrc가
root

```
[ ! -e /etc/bash.bashrc ] || mv -v /etc/bash.bashrc  
/etc/bash.bashrc.NOUSE
```

lfs 가 (7) /etc/bash.bashrc

()

8.35 "Bash-5.2.21"

LFS Bash
LFS

/etc/bash.bashrc
가

가 ()
make

"parallel make"

i9-13900K 8 P() 16 E()

가 , P 2 P 2

가 32 가

make가 32

make -j32

```
make -j32
```

MAKEFLAGS

make

```
export MAKEFLAGS=-j32
```



-j
make가

make

MAKEFLAGS

5 6
MAKEFLAGS

.bashrc

```
cat >> ~/.bashrc << "EOF"  
export MAKEFLAGS=-j$(nproc)  
EOF
```

\$(nproc)

bash

```
source ~/.bash_profile
```

From:
<https://www.gamu.kr/dokuwiki/> -

Permanent link:
https://www.gamu.kr/dokuwiki/linuxfromscratch/12.1/028-setting_up_the_environment?rev=1717490987

Last update: **2024/06/04 08:49**

