

etc/fstab

( )  
:

```

cat > /etc/fstab << "EOF"
# Begin /etc/fstab

# file system  mount-point  type  options  dump  fsck order

/dev/<xxx>    /  <fff>  defaults  1  1
/dev/<yyyy>   swap  swap  pri=1  0  0

# End /etc/fstab
EOF

```

<xxx>, <yyy>, <fff> ( : sda2, sda5, ext4) . 6  
fstab(5)

MS-DOS Windows ( : vfat, ntfs, smbfs, cifs, iso9660, udf)  
ASCII가 가 utf8 . utf8  
iocharset  
(kernel config File System → Native Language Support  
)가 UTF-8  
iocharset=utf8  
UTF-8 iocharset=utf8 utf8 . vfat smbfs  
"codepage" 가 MS-DOS  
, USB ru\_RU.KOI8-R /etc/fstab  
:

```
noauto,user,quiet,showexec,codepage=866,iocharset=koi8r
```

ru\_RU.UTF-8 :

```
noauto,user,quiet,showexec,codepage=866,utf8
```

iso8859-1 iocharset  
utf8 UTF-8 UTF-8  
iocharset  
"Default NLS Option"(CONFIG\_NLS\_DEFAULT), "DefaultRemote NLS  
Option"(CONFIG\_SMB\_NLS\_DEFAULT), "Default codepage for  
FAT"(CONFIG\_FAT\_DEFAULT\_CODEPAGE), "Default iocharset for  
FAT"(CONFIG\_FAT\_DEFAULT\_IOCHARSET) . ntfs

ext3  
/etc/fstab barrier=1 가 가  
hdparm

```
hdparm -I /dev/sda | grep NCQ
```

가

: LVM( ) barrier

From: <https://www.gamu.kr/dokuwiki/> -

Permanent link: [https://www.gamu.kr/dokuwiki/linuxfromscratch/12.1/165-creating\\_the\\_etcfstab\\_file?rev=1714389041](https://www.gamu.kr/dokuwiki/linuxfromscratch/12.1/165-creating_the_etcfstab_file?rev=1714389041)

Last update: **2024/04/29 11:10**

